

Instructions for Backup Configuration Function

In the “Software Update & Reinstallation” menu there is a function called “Backup Configuration”. This function will let you save settings made in the “Installation & Settings” menu, and all your channel lists, to a USB memory stick.

Here is a short instruction on how to use the backup function:

1. Place an empty USB memory stick in any of the four USB ports.
2. Go to the menu “Installation & Settings”, press “Software Update & Reinstallation” followed by pressing the option “Backup Configuration”.
3. Select the inserted USB memory and press “OK”.
4. Your settings are now saved.
5. Remove the USB memory from the USB port.

Load settings after software upgrade:

When you want to load your saved settings (such as after software upgrade), just insert the USB memory into any USB port and do a reinstallation. Your settings will be loaded again.

Load settings:

If you want to load your settings without doing a reinstallation, just insert the USB memory into any USB port and restart the LyngBox.